Fujitsu VDI Bundle for VMware
Your network configuration

Please complete the information before you start the setup process.
For detailed information refer to VDI Bundle Implementation Guide.
See *http://ts.fujitsu.com/support/manuals.html* and select from product line "Zero Clients" or "Thin Clients" your product of the according Futro Series..



Not included!

LAN

Router for internet access.

Disable DHCP and set a static IP-Address.

Network configuration

IP-Address: _____

Subnetmask: _____

2 PC for server administration.

Network configuration

IP-Address: _____

Subnetmask: _____

Software requirements:

- ❑ Windows 7 and Internet Explorer 9 or higher
- ❑ .Net Framework 3.5 or higher
- ❑ Adobe Flash Player 10 or higher
- ❑ VMware vSphere Client

3 MS Windows Server 2012 or 2008R2

Domain configuration

Hostname: _____

Domainname: _____

Network configuration

IP-Address: _____

Subnetmask: _____

Default-Gateway: _____

Primary-DNS-Server: _____

DHCP configuration

Scope-Name: _____

IP-Address range:

_____ - _____

4 Vmware vCenter Server Appliance

Network configuration

IP-Address: _____

Subnetmask: _____

Default-Gateway: _____

Primary-DNS-Server: _____

Domain-Suffix: _____

empty virtual machines for e.g.

Network configuration via DHCP

5 Teradici PCoIP Mgmt. Console

Network configuration

IP-Address: _____

Subnetmask: _____

Default-Gateway: _____

Primary-DNS-Server: _____

Domain-Suffix: _____

Web interface password

Admin password: _____



TX200 with ESXi UFM device

1 ESXi Server

Network configuration

IP-Address: _____

Subnetmask: _____

Default-Gateway: _____

Primary-DNS-Server: _____

Hostname: _____

DomainSuffix: _____

Fujitsu VDI Bundle for VMware
Example network configuration

Please complete the information before you start the setup process.
For detailed information refer to VDI Bundle Implementation Guide.
See *http://ts.fujitsu.com/support/manuals.html* and select from product line "Zero Clients" or "Thin Clients" your product of the according Futro Series.



Order No. Fujitsu Technology Solutions GmbH: A26361-F2009-Z300-1-8N19, Edition 3

A26361-F2009-Z300-1-8N19

Step1
- Unbox all components and prepare hypervisor hardware (server)
- Plan your installation and complete "Your network configuration" template
- Prepare Management PC and Internet Router - not included in package

Step2
- Connect all cables such as LAN and power cable, keyboard and monitor to hypervisor hardware
  > power on server

Step3
- Initial configuration of hypervisor
  > set default password, network and keyboard configuration

Step4
- Install VMware vSphere Client
  > follow download link on hypervisors website and install on your management computer

Step 5
- Configure datastores of hypervisor
  > start vSphere Client and add datastore

Step 6
- Inventory of preinstalled virtual machines
  > vSphere Client: browse datastores and inventory of prepared virtual machines

Step 7
- Set up Microsoft Windows Server
  > start virtual Windows Server and finish installation
  > setup Active Directory, DNS and DHCP scope and options

Step 8
- Initial setup of VMware vCenter Server Appliance
  > power on, set up default password and network configuration
  > vCenter Server web-console: set up directory and virtualization configuration.

Step 9
- (optional) Initial setup of Teradici PCoIP Management Console
  > power on, set up network configuration and change web interface password
  > PCoIP Management web-console: manage your PCoIP clients (e.g. Futro L420 / L620, ...)

Step 10
- Prepare Desktop Virtual Machines (DVMs)
  > assign installation media (XP/Win7) to virtual machines CD drive and start installation
  > add to domain, install VMware Tools.

Step 11
- Connect VDI Client Devices
  > configure VDI clients

For detailed information refer to VDI Bundle Implementation Guide. See *http://ts.fujitsu.com/support/manuals.html* and select from product line "Zero Clients" or "Thin Clients" your product of the according FUTRO Series.